1. **Text** : Used to display text with its appropriate formatting options/properties as given below.

SNo	Property/Style Name	Caption	Type	Description Values
1	Title	Title	Text	To enter the text value. Max length : 100. By default, 'text' is displayed.
2	TextSize	Text Size	Select	Default(H6) - fontSize 14. Can choose size (H1-H6) from the drop down in the decreasing order from H1 to H6.
3	Width	Width	Number,Select	Choose appropriate width for the text control by entering a number.
4	Height	Height	Number,Select	Choose appropriate height for the text control by entering a number.
5	Color	Color	Picker	To choose text color. Default : blue
6	BackgroundColor	Background Color	Picker	To choose background color within the dimensions of the text.
7	borderWidth	Border Width	Number,Select	Choose width of a border for your text.Select value number (0 to 5)
8	borderRadius	Border Radius	Number,Select	Select value number (0 to 100)
9	borderStyle	Border Style	Select	To design the border for your text viz dotted,dashed,solid.
10	borderColor	Border Color	Picker	Pick a color for a border around the text.
11	textAlign	Text Align	Select	To align your text.(Auto,left,right,center ,justify)
12	fontSize	Font Size	number, Select	To set the size of the text from0 to 36.
13	fontFamily	Font Family	Select	To choose style for text from the options available in the drop down.
14	fontWeight	Font Weight	Select	To bold/unbold text. Default : Normal.
15	margin	Margin	Number,Select	Enter number to choose the margin.
16	marginLeft	Margin Left	Number,Select	To choose margin length from the left of the screen.
17	marginRight	Margin Right	Number,Select	To choose margin length from the right of the screen.

18	marginTop	Margin Top	Number,Select	To choose margin length from the top of the screen.
19	marginBottom	Margin Bottom	Number,Select	To choose margin length from the bottom of the screen.
20	padding	Padding	Number,Select	To choose the space between the margin and text.
21	paddingLeft	Padding Left	Number,Select	To choose the space from left between the margin and text.
22	paddingRight	Padding Right	Number,Select	To choose the space from right between the margin and text.
23	paddingTop	Padding Top	Number,Select	To choose the space from top between the margin and text.
24	paddingBottom	Padding Bottom	Number,Select	To choose the space from bottom between the margin and text.