

- 1. Header:** Header control is to define the header tab which could consist of the properties as mentioned below.

SNo	Property/Style Name	Caption	Type	Description Values
1	title	Title	Text	Enter the name for your header.'Header' would be displayed by default.
2	headerstyle	Type	select	Enter font style for Header from the drop down.
3	displaylefticon	Need Left Icon	Checkbox	To display properties relating to left icon. If enabled, enable lefticon,lefticoncolor,lefticonsize and lefticonpress event. Default - true
4	lefticon	Left Icon	select	Choose the icon to be displayed as left icon w.r.t.the action being performed. (Menu,format-align justify,keyboard backspace)
5	lefticoncolor	Left Icon Color	Picker	Choose color for the icon.
6	lefticonsize	Left Icon Size	Select	Choose the size of icon.
7	lefticonsizevalue	Custom	Number,Select	Choose the size of the icon by entering a custom number.
8	displayrighticon1	Need Right Icon 1	Checkbox	To display properties relating to right icon. If enabled, enable righticon, righticoncolor, righticonsize and righticonpress event.
9	righticon1	Right Icon1	select	Choose from the list of actions that couldbe performed. The options are logout, account,settings-outline, home ,magnify,dots-vertical. Style 3 "magnify" icon is set as default
10	righticon1color	Right Icon1 Color	Picker	Color of the icon
11	righticon1size	Right Icon1 Size	Number,Select	Size of the icon. Default - Small.
12	righticon1sizevalue	Custom	Number,Select	Can enter a custom number with min 10 and max 50.
13	displayrighticon2	Need Right Icon 2	Checkbox	To enable icon on the right of he header.If enabled, enable righticon2,righticon2color,righticon2size

				properties and righticon2press event. Default - true.
14	righticon2	Right Icon2	select	Choose from the drop down as mentioned earlier. 'Dots Vertical' set as default.
15	righticon2color	Right Icon2 Color	Picker	Color of the icon
16	righticon2size	Right Icon2 Size	Number,Select	Size of the icon. Default - Small.
17	righticon2sizevalue	Custom	Number,Select	Can enter a custom number with min 10 and max 50.
18	displayrighticon3	Need Right Icon 3	Checkbox	To enable icon on the right of the header.If enabled, enable righticon3,righticon3color,righticon3size properties and righticon2press event. Default - false.
19	righticon3	Right Icon3	select	Choose from the drop down as mentioned earlier.
20	righticon3color	Right Icon3 Color	Picker	Color of the icon
21	righticon3size	Right Icon3 Size	Number,Select	Size of the icon. Default - Small.
22	righticon3sizevalue	Custom	Number,Select	Can enter a custom number with min 10 and max 50.
23	addicon	Add	Icon	Used to add additional icons in the right side.Max 3 icons are allowed
24	imagetype	Background Image Type	Select	Values - URL and Path. Default value is URL.
25	backgroundImage	Header Background Image	URL/Path	It is based on the Background Image Type value.You can give URL Path of the image or path of the image source (Supported format png, jpg - preferable png).
26	backgroundColor	Header Background Color	Picker	Choose header background color. Default color is Blue
27	color	Text Color	Picker	Choose header text color. Default color is White
28	fontSize	Font Size	Number,Select	Min - 0 and Max - 50. Default value is 20

29	fontFamily	Font Family	Select	Choose from drop-down.
30	fontWeight	Font Weight	Select	Values - bold and normal. Default - normal
31	textAlign	Text Align	Select	Values - center. Default is empty.
32	margin	Margin	Number,Select	Enter number to choose the margin.
33	marginLeft	Margin Left	Number,Select	To choose margin length from the left of the screen.
34	marginRight	Margin Right	Number,Select	To choose margin length from the right of the screen.
35	marginTop	Margin Top	Number,Select	To choose margin length from the top of the screen.
36	marginBottom	Margin Bottom	Number,Select	To choose margin length from the bottom of the screen.